

Colette
PATTERNS

3001
SWEATER COAT
OSLO




INSTRUCTIONS




YOU WILL NEED:

- *Oslo Pattern*, from *Seamwork Magazine*
- *Large paper for tracing*
- *Clear tape*
- *Pencil or pen*
- *Ruler*
- *French Curve*


SUBSECTION




1. Trace bodice front (A), bodice back (B), and sleeve (C), eliminate seam allowances ($\frac{3}{8}$ ").




2. Draw a line from the center sleeve circle to the sleeve hem, parallel to the grainline. Cut along the drawn line.




3. Draw a line continuing the front shoulder seam. Place front half of sleeve so the centerline touches the shoulder continuation line, and the sleeve cap butts up to the armhole.




4. Repeat step 3 on back bodice and sleeve.



5. Use a french curve to draw a gentle curve at the underarm.



6. Repeat on the second bodice/sleeve unit.



7. Add seam allowance.

8. Create belt loops by cutting two 1 1/2" by 5" rectangles of your fabric. Fold right side together, along the length of the rectangle. Stitch at 1/4" and turn right side out. Baste belt loops to the right side of the front bodice side seam at the waist.
9. To create belt, cut two 30"x 4.5" pieces of fabric. Join two short ends together, forming one long belt. Fold right side together, along the length of the belt. Pin to secure. Sew along the short and long edge of the belt, leaving a 5" hole at the center. Pull belt right side out through opening, hand stitch to finish.
10. Assemble pattern according to pattern instructions, omitting the sleeve cuff.

STILL NEED YOUR PATTERN? PICK IT UP AT [SEAMWORKMAG.COM/CATALOG/OSLO](https://seamworkmag.com/catalog/oslo)